



MICRON IP NVR SHARING INSTRUCTIONS

Step 1. Sharing the NVR to an existing P2P User via email address.



Step 2.




After opening the app tap on the options menu at the top left of the screen.

Tap on the "P2P Account" link at the top of the screen


MICRON IP NVR SHARING INSTRUCTIONS

Step 3.



Tap on the “My Devices” link


Step 4.



Select the NVR then select the “Share” option at the bottom

MICRON IP NVR SHARING INSTRUCTIONS


Step 5.



Tap the "Share To" option, a box will appear. Enter the email address of the P2P User that you would like to share the NVR To and select OK

Then Tap the "Share" button. The NVR will now appear in the users devices.

SHARING OPTION 2: VIA QR CODE



Select the "QR Code" tab, then create a sharing password (any password) for the NVR.

Select the user authority level, then select Generate to create a QR sharing code.

MICRON IP NVR SHARING INSTRUCTIONS



To Share the NVR with other users you may now scan this code using the add p2p device options discussed earlier. I.E.

- **Select P2P Account**
- **My devices**
- **Add P2P Device**
- **Select the Scan option and scan the QR code generated above.**
- **Enter the sharing password created earlier.**

Technical Notes

Alternative method of setting up a P2P account from Website

If you are unable to setup a P2P account from the mobile device, or do not receive the verification code, you can create an account directly on the star4live website. To do this go to:

www.star4live.com

Select the “sign up” link at the top right of screen

Enter your preferred username and a password information

Enter your email address and select “acquire”

An email will be sent with your verification code to be entered into the verification code box.

Ensure you have ticked the “I agree to service agreement” box and select “sign up” to complete your registration.

This information can now be used to login to your p2p account on your mobile device.